

Pathfinder MapEdge™ - Screen Layout

1. Button Layout Options

You can change the button layout using the *Option > Button Layout* menu commands. There are two sets of choices: a) simple or not simple, and b) left side, right side, top or bottom. The product ships with *Simple* and *Left Side*. The following pictures illustrate the settings:

Buttons: simple, left side



Buttons: simple, top:



Buttons: simple, right side:



Buttons: *not* simple, left side:



These options are provided so that you may select the layout that is most comfortable.

The simple option shows more map by eliminating the N, S, E, etc. buttons and the Oldest, Newest, etc. layer buttons. The Oldest, Newest, etc. layer buttons are rarely used and the functionality of the N, S, E, etc. buttons can be accomplished by the Pan (hand) button or using the keyboard arrow keys together with <Shift> or <Ctrl>.

2. Screen Layout Description

The screenshot shows the Pathfinder MapEdge 2005 interface with the following numbered callouts:

- 1 Zoom In 2x
- 2 Zoom Out 2x
- 3 Zoom by Rectangle
- 4 Pan Main Window
- 5 Copy Entire Window
- 6 Copy Rectangle
- 7 Tape/Spaghetti Measure
- 8 Radius Measure
- 9 Status Line
- 10 Street NUMBER Entry
- 11 Street SEGMENT List
- 12 Street NAME Entry
- 13 Intersection List
- 14 Layer Item List
- 15 Layer Name
- 16 Layer Selection (Up/Down)
- 17 Main Window Coverage (Red Rectangle)
- 18 Overview Window
- 19 Main Window
- 20 RIGHT Click Menu
- 21 Previous View and Next View
- 22 West, North Pan
- 23 Next (Newer) Item
- 24 OLDEST Item In Layer List
- 25 Print
- 26 NEWEST Item in Layer List
- 27 Previous (Older) Item